

# Load Fields Into Widgets

Allows database driven grids to load their data into widgets. This method loads the data a page at a time. To generate this grid as a load-all see: [load all rows](#)

**Promptable?** DROPDOWN

**Possible Values:** true, false


**Bindable?** No

**Products:** ProfoundUI

*Available in Profound UI Version 6 Fix Pack 8.0.*

## Set up

To use, the grid should be set up with widgets to hold the data in each column, with the chosen database-driven method. The widgets should be bound, and the binding name should match the column name from the table.



In this example, the "database file" method will be used.

database file	PUISAMPLES/POSTP
database fields	POSTCITY,POSTSTATE,POSTZ

## Loading data into widgets

To load the data into the widgets, set the "load fields into widgets" property to true.

load fields into widgets	true
--------------------------	------

Now the data can be formatted using any of the widget properties. For example, here the color is set to red, the text centered, and a 1000s separator added to the numerical data.

value	POSTSTATE
<b>Font and Text</b>	
color	red
font family	
font size	
font style	
font variant	
font weight	
letter spacing	
text align	center

OutputField3\_copy3 - Bind Value to a Program Field

Field Name	Data Type	Reference Field
POSTZIP	Use Reference Field	POSTZIP
<b>Field Formatting</b>		
<input checked="" type="checkbox"/> Use 1000 Separator	Edit Word	
<input type="checkbox"/> Show Zero Balance	Edit Mask	
<input type="checkbox"/> Blank Fill	Currency Symbol	
<input type="checkbox"/> Zero Fill	Units	
<input type="checkbox"/> No extra spaces	Negative Numbers	
	-999.00	

postcity _	poststate _	postzip	postname
ANAKTUVUK	AK	99,721	<input type="text" value="NORTH SLOPE"/>
ANAKTUVUK PASS	AK	99,721	<input type="text" value="NORTH SLOPE"/>
ANCH	AK	99,505	<input type="text" value="ANCHORAGE"/>
ANCHOR POINT	AK	99,556	<input type="text" value="KENAI PENINSULA"/>
ANCHORAGE	AK	99,501	<input type="text" value="ANCHORAGE"/>